

## Php Pdf Add-ons - Defect #585

### Tables spanning several pages starts to break apart...

01/15/2014 02:49 PM - Joe Privett

<b>Status:</b>	Closed	<b>Start date:</b>	01/15/2014
<b>Priority:</b>	High	<b>Due date:</b>	
<b>Assignee:</b>	Joe Privett	<b>% Done:</b>	0%
<b>Category:</b>		<b>Estimated time:</b>	0.00 hour
<b>Target version:</b>			

#### Description

I have generated a PDF (attached) containing a table using the code below. Problem is that after the table crosses a few pages, it starts to break-up - do you know why?

```
$num_columns = 4;
$table = new tfpdfTable($pdf_report);
$table->initialize(array(70,90,55,55), $table_2_config);

$row = array();
$row[0]['TEXT'] = stripslashes($row_cat['ra_hazard_category']);
$row[0]['TEXT_COLOR'] = array(255,255,255);
$row[0]['TEXT_SIZE'] = 14;
$row[0]['LINE_SIZE'] = 6;
$row[0]['BACKGROUND_COLOR'] = array(53,53,53);
$row[0]['COLSPAN'] = 4;
$table->addRow($row);

$row = array();
$row[0]['TEXT'] = "Hazard";
$row[0]['TEXT_TYPE'] = 'B';
$row[0]['BACKGROUND_COLOR'] = array(241,241,241);
$row[1]['TEXT'] = "Existing Control Measure(s)";
$row[1]['BACKGROUND_COLOR'] = array(241,241,241);
$row[1]['TEXT_TYPE'] = 'B';
$row[2]['TEXT'] = "Category of Harm";
$row[2]['BACKGROUND_COLOR'] = array(241,241,241);
$row[2]['TEXT_TYPE'] = 'B';
$row[3]['TEXT'] = "Likelihood of Harm";
$row[3]['BACKGROUND_COLOR'] = array(241,241,241);
$row[3]['TEXT_TYPE'] = 'B';
$table->addRow($row);

for($h=0;$h <count($haz_title_array);$h++){

    $row = array();
    $row[0]['TEXT'] = $haz_title_array[$h];
    $row[1]['TEXT'] = $secm_text_array[$h];
    $row[2]['TEXT'] = $ra_harm_category_array[$h];
    $row[3]['TEXT'] = $ra_harm_likelihood_title_array[$h];
    $table->addRow($row);

}

$table->close();
```

#### History

#1 - 01/15/2014 02:57 PM - Andrei Bintintan

- Status changed from New to Feedback

- Assignee changed from Andrei Bintintan to Joe Privett

This usually happens when the page-break is NOT triggered by the table.

1. Which table version are you using?
2. Try to disable header/footer functions and see if it's working.

If 2 solves your issue, make sure that your header function is NOT changing the Y value after exit.

If still not ok, let me know, it also might be a bug.

**#2 - 01/16/2014 12:40 PM - Joe Privett**

I'm using version 4.0.6 - can I get a free upgrade if there is a newer version?

**#3 - 01/16/2014 12:42 PM - Joe Privett**

Where do I disable the header and footer functions?

**#4 - 01/20/2014 08:19 PM - Andrei Bintintan**

Joe Privett wrote:

I'm using version 4.0.6 - can I get a free upgrade if there is a newer version?

That version is very old and is not supported anymore. You can get the latest version here: <http://www.interpid.eu/download>

Where do I disable the header and footer functions?

If you have defined them, look for -> Header() and Footer() function in the main pdf class.

**#5 - 07/07/2016 10:12 AM - Andrei Bintintan**

- Status changed from Feedback to Closed

**Files**

---

doc.4-21.pdf	177 KB	01/15/2014	Joe Privett
--------------	--------	------------	-------------